

Quarkus - Reading properties from Spring Cloud Config Server

This guide explains how your Quarkus application can read configuration properties at runtime from the [Spring Cloud Config Server](#).



This technology is considered preview.

In *preview*, backward compatibility and presence in the ecosystem is not guaranteed. Specific improvements might require to change configuration or APIs and plans to become *stable* are under way. Feedback is welcome on our [mailing list](#) or as issues in our [GitHub issue tracker](#).

For a full list of possible extension statuses, check our [FAQ entry](#).

Prerequisites

To complete this guide, you need:

- less than 15 minutes
- an IDE
- JDK 1.8+ installed with `JAVA_HOME` configured appropriately
- Apache Maven 3.6.3

Solution

We recommend that you follow the instructions in the next sections and create the application step by step.

Stand up a Config Server

To stand up the Config Server required for this guide, please follow the instructions outlined [here](#). The end result of that process is a running Config Server that will provide the `Hello world` value for a configuration property named `message` when the application querying the server is named `a-bootiful-client`.

Creating the Maven project

First, we need a new project. Create a new project with the following command:

```
mvn io.quarkus:quarkus-maven-plugin:1.8.0.CR1:create \  
  -DprojectId=org.acme \  
  -DprojectId=spring-cloud-config-quickstart \  
  
-DclassName="org.acme.spring.cloud.config.client.GreetingResource" \  
\  
  -Dpath="/greeting" \  
  -Dextensions="spring-cloud-config-client" \  
cd spring-cloud-config-quickstart
```

This command generates a Maven project with a REST endpoint and imports the `spring-cloud-config-client` extension.

If you already have your Quarkus project configured, you can add the `spring-cloud-config-client` extension to your project by running the following command in your project base directory:

```
./mvnw quarkus:add-extension -Dextensions="spring-cloud-config-client"
```

This will add the following to your `pom.xml`:

```
<dependency>  
  <groupId>io.quarkus</groupId>  
  <artifactId>quarkus-spring-cloud-config-client</artifactId>  
</dependency>
```

GreetingController

The Quarkus Maven plugin automatically generated a `GreetingResource` JAX-RS resource in the `src/main/java/org/acme/spring/cloud/config/client/GreetingResource.java` file that looks like:

```

package org.acme.spring.spring.cloud.config.client;

import javax.ws.rs.GET;
import javax.ws.rs.Path;
import javax.ws.rs.Produces;
import javax.ws.rs.core.MediaType;

@Path("/hello")
public class GreetingResource {

    @GET
    @Produces(MediaType.TEXT_PLAIN)
    public String hello() {
        return "hello";
    }
}

```

As we want to use configuration properties obtained from the Config Server, we will update the `GreetingResource` to inject the `message` property. The updated code will look like this:

```

package org.acme.spring.spring.cloud.config.client;

import javax.ws.rs.GET;
import javax.ws.rs.Path;
import javax.ws.rs.Produces;
import javax.ws.rs.core.MediaType;

import org.eclipse.microprofile.config.inject.ConfigProperty;

@Path("/hello")
public class GreetingResource {

    @ConfigProperty(name = "message", defaultValue="hello default")
    String message;

    @GET
    @Produces(MediaType.TEXT_PLAIN)
    public String hello() {
        return message;
    }
}

```

Configuring the application

Quarkus provides various configuration knobs under the `quarkus.spring-cloud-config` root. For the purposes of this guide, our Quarkus application is going to be configured in

`application.properties` as follows:

```
# use the same name as the application name that was configured
when standing up the Config Server
quarkus.application.name=a-bootiful-client
# enable retrieval of configuration from the Config Server - this
is off by default
quarkus.spring-cloud-config.enabled=true
# configure the URL where the Config Server listens to HTTP
requests - this could have been left out since
http://localhost:8888 is the default
quarkus.spring-cloud-config.url=http://localhost:8888
```

Package and run the application

Run the application with: `./mvnw compile quarkus:dev`. Open your browser to <http://localhost:8080/greeting>.

The result should be: `Hello world` as it is the value obtained from the Spring Cloud Config server.

Run the application as a native executable

You can of course create a native image using the instructions of the [Building a native executable guide](#).

More Spring guides

Quarkus has more Spring compatibility features. See the following guides for more details:

- [Quarkus - Extension for Spring DI](#)
- [Quarkus - Extension for Spring Web](#)
- [Quarkus - Extension for Spring Data JPA](#)
- [Quarkus - Extension for Spring Security](#)
- [Quarkus - Extension for Spring Boot properties](#)
- [Quarkus - Extension for Spring Cache](#)
- [Quarkus - Extension for Spring Scheduled](#)

Spring Cloud Config Client Reference

 Configuration property fixed at build time - All other configuration properties are overridable at runtime

Configuration property	Type	Default
<p><code>quarkus.spring-cloud-config.enabled</code></p> <p>If enabled, will try to read the configuration from a Spring Cloud Config Server</p>	boolean	<code>false</code>
<p><code>quarkus.spring-cloud-config.fail-fast</code></p> <p>If set to true, the application will not stand up if it cannot obtain configuration from the Config Server</p>	boolean	<code>false</code>
<p><code>quarkus.spring-cloud-config.url</code></p> <p>The Base URI where the Spring Cloud Config Server is available</p>	string	<code>http://localhost:8888</code>
<p><code>quarkus.spring-cloud-config.connection-timeout</code></p> <p>The amount of time to wait when initially establishing a connection before giving up and timing out. Specify <code>0</code> to wait indefinitely.</p>	Duration 	<code>10S</code>
<p><code>quarkus.spring-cloud-config.read-timeout</code></p> <p>The amount of time to wait for a read on a socket before an exception is thrown. Specify <code>0</code> to wait indefinitely.</p>	Duration 	<code>60S</code>
<p><code>quarkus.spring-cloud-config.username</code></p> <p>The username to be used if the Config Server has BASIC Auth enabled</p>	string	
<p><code>quarkus.spring-cloud-config.password</code></p> <p>The password to be used if the Config Server has BASIC Auth enabled</p>	string	
<p><code>quarkus.spring-cloud-config.trust-store</code></p> <p>TrustStore to be used containing the SSL certificate used by the Config server Can be either a classpath resource or a file system path</p>	path	
<p><code>quarkus.spring-cloud-config.trust-store-password</code></p> <p>Password of TrustStore to be used containing the SSL certificate used by the Config server</p>	string	
<p><code>quarkus.spring-cloud-config.key-store</code></p> <p>KeyStore to be used containing the SSL certificate for authentication with the Config server Can be either a classpath resource or a file system path</p>	path	

<code>quarkus.spring-cloud-config.key-store-password</code>		
Password of KeyStore to be used containing the SSL certificate for authentication with the Config server	string	
<code>quarkus.spring-cloud-config.key-password</code>		
Password to recover key from KeyStore for SSL client authentication with the Config server If no value is provided, the key-store-password will be used	string	
<code>quarkus.spring-cloud-config.trust-certs</code>		
When using HTTPS and no keyStore has been specified, whether or not to trust all certificates	boolean	<code>false</code>

About the Duration format

The format for durations uses the standard `java.time.Duration` format. You can learn more about it in the [Duration#parse\(\) javadoc](#).



You can also provide duration values starting with a number. In this case, if the value consists only of a number, the converter treats the value as seconds. Otherwise, `PT` is implicitly prepended to the value to obtain a standard `java.time.Duration` format.